




# Puca Bracelet

## MATERIALS:

1. **(KP)** Kheops Puca beads (# KHP06-03000)
2. **(SD)** SuperDuo beads (# DU0500030-27000-TB)
3. **(MB)** Matubo beads (# MTB07-00030-27000)
4. **(RII, RI5)** 11/0 and 15/0 Seed Beads (# MT11-SLV-TB, # MT15-SLV-TB)
5. **(FPR)** 4mm Fire Polished Rounds (# FPR04MIX08)
6. **(BC)** 4mm Swarovski Bicones (# 532804CSS)
7. Elegant Elements Push Pull Clasp (# CLSP64SP)
8. 6 lb Fireline in Crystal (# FL06CRI25 )
9. #10 Beading Needle (# BN10)
10. Jump rings
11. Wire Protectors (# WG01SP)

## DIRECTIONS:

1. Leaving a 4" tail of fireline, thread 1 KP, 1 MB, 1 KP, 1 SD, 1 MB, 1 SD, 1 KP, 1 MB, 1 KP : making sure that you pass the needle through the Kheops Puca beads as seen in **(image 1)**.
2. Take needle and pass back through the last SuperDuo's unused hole. **(image 2)**
3. Thread 1 MB, and pass needle through the next Superduos unused hole. **(image 3)**
4. Now pass needle through the 1st KP bead. **(image 4)**
5. Now take a second pass following **(image 5)** as your path.
6. Thread 1 FPR, 1 MB, 1 FPR and Loop back though the Matubo you came out of. Pass the thread through the entire loop again to re-inforce it, and then one more time through the 1st FPR and end coming out of the Matubo at the top. **(image 6)**





7. Thread 1 KP, 1 SD, 1 MB, 1 SD, 1 KP, 1 MB, 1 KP as shown in **(image 7)**.



8. Same as in step 2 & 3 you are going to pass the needle through the last Superduos unused hole, add 1 MB, and then pass through the other superduos unused hole. **(image 8)**



9. Thread 1 KP as shown in **(image 9)**.

10. Following the path shown in **(image 10)**, make a second pass through the last few beads, and end coming out the Matubo bead.



11. Repeat steps 6-10 until your bracelet is your desired length.

12. Thread 2 x R15, 1 R11, 2 x R15 and pass around tip of Kheops Puca bead and through its unused hole, as seen in **(image 11)**.



13. Thread 1 R11, 1 FPR, 1 R11 and pass through next Kheops Puca beads hole. **(image 12)**

14. Thread 1 R15, 1 R11, 1 BC, 1 R11, 1 R15 and go through the next Kheops Puca bead's hole. **(image 13)**







15. Alternate steps 12 & 13 until you reach the end of that side. Thread 2 x R15, 1 R11, 2 x R15 and go around the tip of the Kheops Puca and through the middle Matubo Bead. Then thread 2 x R15, 1 R11, 2 x R15 and go around the other Kheops Puca and through its unused hole. **(image 14)**



16. Repeat steps 12 -13 alternating down the other side until you come out the last Kheops Puca.

17. Thread 2 x R15, 1 R11, 2 x R15 go around the tip of the Kheops Puca and through the middle Matubo bead. **(image 15)**

18. Thread 1 R15, A wire protector and another R15 and pass back through the Matubo. **(image 16)**

19. For good measure make one more pass up through the seed beads and wire protector and back out the Matubo.

20. Follow back through the seed beads into the Kheops Puca and down one side until you come back out the last Puca Bead and through the seed beads on that side to end coming out the matubo bead in the middle.

21. Add 1 R15, 1 wire protector and 1 R15 and go back through the Matubo. Pass through that twice to reinforce the wire protector. Both of your bracelet ends should now be finished and appear like **(image 17)**. Make a knot and cut off the remainder of the thread.

22. Add your clasp using jumprings to the wire protectors on both sides.

